

```

1 *****
2 *
3 *      FinderFileLoader - An AppleWorks Init      *
4 *      (for AppleWorks Version 5.1)              *
5 *
6 *      - Adds Up to 36 Files to AppleWorks Desktop *
7 *      at one time when files are selected and   *
8 *      opened from within GS/OS Finder          *
9 *
10 *      - Init must be present in the AppleWorks  *
11 *      inits directory                          *
12 *      (e.g. /HD/AppleWorks/AW.Inits)          *
13 *      - Init Manager must be activated in     *
14 *      AppleWorks 'Standard Settings' Menu     *
15 *
16 *      - Use an Icon Editor to point AWP/ASP/ADB *
17 *      (and optionally TXT and *.S) files to   *
18 *      'APLWORKS.SYSTEM' to auto-run          *
19 *      AppleWorks AND load the files to the    *
20 *      Desktop when (1) of more of those      *
21 *      type files are selected and opened     *
22 *      from the GS/OS Finder                  *
23 *
24 *      - The names of the files selected in the *
25 *      Finder are retrieved from the GS/OS 'MessageCenter' *
26 *      by a machine language routine loaded into *
27 *      memory by a compiled UltraMacros Task File *
28 *      that is in turn loaded into memory by   *
29 *      this AppleWorks Init. The files are then *
30 *      automatically loaded to the AppleWorks  *
31 *      Desktop                                *
32 *
33 *      based on the AppleWorks 3/UltraMacros 'FinderLaunch' *
34 *      by John L. Tegelaar & Ton W. van Santen *
35 *      The Netherlands (1991)                *
36 *
37 *      by Hugh Hood                            *
38 *      Version 1.4 (2024)                     *
39 *
40 *****

```

```

41
42      TR          ADR          ; truncate bank address
43
44      XC          ; enable 65C02 code
45
46 * Equates *
47
48 Seg00Type      EQU          $FE0          ; memory manager type
49                                     ; $41 = SEG.AM / $52 = SEG.RM (IIGS) /
50                                     ; $58 = SEG.XM / $4D = Deja IIX (Mac)
51 AWVersion      EQU          $1003        ; $33/51 = 5.1 / $28/40 = 4.0 /
52                                     ; $1E/30 = 3.0
53 TaskFileStart  EQU          $11B1        ; $00 = load and use default macros;
54                                     ; $01 = use pre-loaded task file macros
55 InitAdr        EQU          $4000        ; load address for Init files
56 MainZP         EQU          $C008        ; Main Zero Page (AppleWorks)
57 AuxZP          EQU          $C009        ; Aux Zero Page (UltraMacros)
58 MoveToAux      EQU          $D076        ; Move from Main to Aux

```



```
117 ; $100-$300) bytes after for the
118 ; Macro Titles Table
119 ; - only EF00-$FEFF macro table
120 ; will be moved and no additional
121 ; Desktop memory will be used
122
123 InitEnd EQU *
124
125 SAV I.FINDERFILELDR
126 LST OFF
127
128 END
129
```